

**GoldMine INI file Settings**

File	Section	FieldName	Value(s)	Description
GM	[AutoMaintain]	FileList=	File flags	Set in Tools/Maintain /AutoMaint menu
GM	[AutoMaintain]	LastRun=	Days between runs	Set in Tools/Maintain /AutoMaint menu
GM	[AutoMaintain]	Options=	File options (index only or pack)	Set in Tools/Maintain /AutoMaint menu
GM	[AutoMaintain]	StartTime=	HH:MM	Set in Tools/Maintain /AutoMaint menu
GM	[AutoMaintain]	User=	User name	Set in Tools/Maintain /AutoMaint menu
GM	[GoldMine]	AllowDupAddresses=	0/1	(Don't)Accept duplicate e-mail addresses. See 1202 notes.
GM	[GoldMine]	AllowDupEmails=	0/1	(Don't)Accept duplicate e-mail addresses. GoldMine 4.00.822 and prior allowed duplicate E-mail address but that has changed for 4.00.1202 and greater. Duplicate addresses are no longer supported by default. See Kbase.
GM	[GoldMine]	APProcess=	0/1	?? 1->Automated process activated.
GM	[GoldMine]	AutoLog=	0/1/2	1->Automatically by-passes the login screen and goes directly into GoldMine. User= must also be specified in the GM.INI The user specified cannot have a password or GoldMine will not automatically login.  2->Performs the same function as above but GoldMine is minimized.
GM	[GoldMine]	BDEConfigCheck=	0/1(Default is 1)	Prevents/enablesGM from automatically correcting BDE entries. See Factsback #500.
GM	[GoldMine]	CommitRefreshSec=	##(default=60 for builds 822 and earlier)	Beginning with build 4.0.1202, updates to dBASE tables are now committed to the database as soon as they are made. To gain some performance on write-intensive applications, updates can be cached. See 1202 notes.

GM	[GoldMine]	CommonDir=	Path toCommon data files.	Specifies the location of the contact files directory on a network installation when the exe's and dll's are being run from a local machine. The trailing backslash must be added. Usually X:\GoldMine\Common\.
GM	[GoldMine]	Exclusive=	0/1(default =0)	1 ->instructs GoldMine to open all files in non-sharable mode. Setting this option to 1 is not generally recommended. To open files normally, set equal to 0, which is the default.
GM	[GoldMine]	Golddir=	Path to GMdata files.	Locationof GoldMine files such as Cal.dbf. Usually X:\GoldMine\ orX:\GoldMine\GMBase\.
GM	[GoldMine]	MasterClockMachine=	\\servername	Synchronizeworkstations-clocks to this server's clock every five minutes if UpdateLocalClock=1. Use the time of the master clock for all synchronization time stamps if UpdateLocalClock=0.
GM	[GoldMine]	NameInTitle=	0/1	(Don't)Allow placing the Organization value from the registration in the contact screen title bar.
GM	[GoldMine]	NetIDAPI32DLL=	Path toIDAPI32.DLL	Sets path to this BDE file.
GM	[GoldMine]	NetUpdate=	0/1	?
GM	[GoldMine]	NewComplete=	0/1	ForceGoldMine to create all new records as complete records. GoldMine 4.0 bydefault won't make a complete record until data is inputted into contact2.NOTE: GoldMine 4.00.822 and greater automatically generates Contact2 Records during synchronization when a contact1 record is added to eliminated potential multiple contact2 RecID values for a single contact1 record after synchronization.
GM	[GoldMine]	PBNotifyFreq=	0/#	Disable/Change the number of minutes between periodic updates of the Peg Board.

GM	[GoldMine]	Recover= or Recovery=	1/2	This command is placed in the GM.INI file when GoldMine encounters an error that it determines requires indexing (Recovery=1) or rebuilding GoldMine removes this line once the file(s) have been reindexed or rebuilt properly and GoldMine detects no further errors. 1->Index database on next open.2->Pack & rebuild database on next open.
GM	[GoldMine]	SetCommitRefreshSec=	0	Disable BDE disk caching. Flushes data to disk immediately.
GM	[GoldMine]	SigDir=	Path to folder of signature bitmaps with trailing /.	Allows digitized signatures in Word documents.
GM	[GoldMine]	SQLQueryLimit=	###(default=10,000)	Specify the maximum number of records loaded in the SQL Query list view.
GM	[GoldMine]	SybaseISO=	0/1	For Sybase users, turn off/on ISOLATION 0. Is now off (0) by default. See 1202 notes.
GM	[GoldMine]	SysDir=	Path to GM system folder	Location of system files such as exe & License.dbf. Usually X:\GoldMine\.
GM	[GoldMine]	Transaction=	0/1	Setting to disable/enable transaction processing by background processes. This setting is provided for Oracle 8.05 (or later) when MTXOCI.DLL is used as the Oracle Driver VENDER INIT DLL.?This setting can also eliminate sporadic MS-SQLError 0 messages. See 1202 notes.
GM	[GoldMine]	UpdateLocalClock=	0/1	(Don't)Synchronize all workstations-clocks with the MasterClock.Machine.
GM	[GoldMine]	User=	UserNameor blank	Enters a default (or blank) username in the Username: box at the login screen whenGoldMine is opened.
GM	[GoldMine]	UserINI=	\\UNC path Ex:UserINI=\\srv1\users \%user_id%	Specifythe location of a user's .ini file, allowing the files to be stored in a secure read-only directory. GoldMine will automatically read the logged user and append it to the INI setting using the %USER_ID%

				variable. See 1202 notes.
GM	[GoldMine]	UserLog=	0/1	Track information about how long user has been logged in and the number of mouse clicks, etc. View statistics from File   Configure GoldMine   User's File   Properties   Time Clock.
GM	[NetUpdate]	Exe=	Path to GM4Setup.exe	Tells GM where to look for new setup file if not default of X:\GoldMine\Setup\GoldMine\GM4Setup.exe
GM	[NetUpdate]	LastDate=	Date informat as 19990107160318	Set by GM.Date of last NetUpdate. Used to determine if a GM4Setup file is newer than running version.
GM	[NetUpdate]	Prompt=	0/1	(Don't)Prompt user to install newer version of software if found when-GM4Setup.exe is updated.
GM	[user_var]	FieldName=	Textstring	Defines user variables for all users. The &user_var macro can then be used to merge the field values using an external application, such as Word.
GoldSync	[GoldSync]	AsyncRtrv=	0/1	When usingInternet(Direct),-retrieve the remote's transfer set after the connection is done (0) or right away (1-default). See 1202 notes.
GoldSync	[GoldSync]	COBackupMins=	##(default = 60)	Back up the last cutoff time by n-minutes.
GoldSync	[GoldSync]	IPHandler=	0/1	Thread exception error messages in GoldSync. See 1202 notes.
User	[ActvObj]	AFStampSync=	0/1	1 ->indicates that Mark Updated has been enabled under the Auto-Forward section of the Calendar tab of a user's preferences.
User	[ActvObj]	AlarmsLead=	#	Specifies the alarm lead time in minutes.
User	[ActvObj]	AlarmsOn=	0/1	Turnsalarms off/on.
User	[ActvObj]	AutoForward=	0/1...(repeats6 times)	Specifies which activities to Auto-Forward; specify either 0 to forward or 1 to avoid forwarding for each activity type. The order of activity type is: calls, messages, to dos, appointments, forecasted sales, and other actions. For

				example, to auto-forward all activities except appointments, use the following line: AutoForward=111011
User	[ActvObj]	ConflictOn=	0/1	Turns time conflict checking off/on.
User	[ActvObj]	Range=	#	This setting specifies the date range in the Activity List. 111 is all dates, 112 is today.
User	[ActvObj]	ShowCompany=	0/1	Show the contact/company name in the Activity List in GoldMine 95.
User	[ActvObj]	ShowDetail=	0/1	Instructs GoldMine to (not) show detail information in the Activity List.
User	[ActvObj]	ShowHistActvCode=	0/1	(Don't)Display Activity Code in the History tab.
User	[CalObj]	EndTime=	Time,example: 06:00pm	Specifies time the user ends the workday.
User	[CalObj]	ShowActvs=	#	Specifies which activities will show in the calendar object. The syntax is the same asfor AutoForward= above.
User	[CalObj]	StartTime=	Time,example: 09:00am	Specifies time the user starts the workday.
User	[CommSync]	DelTempDir=	0/1	Leave/Delete the transfer set in the directory after a successful sync. Default is delete.
User	[CommSync]	GSPath=	Path	Specifies the path to the GoldSync GSDATA directory.
User	[CommSync]	LastDialed=	Phonenumber	Stores the last number dialed.
User	[CommSync]	LastRecvPath=	Path	Specifies the last path a transfer set has been retrieved from.
User	[CommSync]	LastSendPath=	Path	Specifies the last path from where a transfer set has been sent
User	[CommSync]	WanTimeOut=	#(default=20)	Instructs GoldMine how long to wait (in seconds) for a response before timing out when synching with GoldSync over a WAN..
User	[FileMenu]	Opt#=	MText,CmdLine,DDECmd,Mnum Ex: Opt1=&Quote,C:\Quote.exe,,8 Opt2=&Letter,,Letter.doc,6	Adds options to GM menus. Replace # with number (order on menu). Place ampersand in front of hot-key in MText. MNum is one of: 1=Filemenu

				<p>2=Edit menu</p> <p>3=Viewmenu, ...</p> <p>9=Helpmenu</p> <p>See Kbase for more info.</p>
User	[FindObject]	FindUSAPhone=	0/1	Disables/Enables searching by telephone numbers in the USA format when working with the Contact Listing. Default is enabled.
User	[GMAAlarm]	CloseOnGMRun=	0/1	1 ->GoldAlarm closes when GoldMine is active. 0 -> GoldAlarm remains in memory.
User	[GMAAlarm]	IgnoreSnooze=	#	Sets the default number of minutes for which an active alarm is ignored.
User	[GMAAlarm]	OKAlarmOnGMRun=	0/1	1 ->Waits for you to click on the OK button before it runs GoldMine.
User	[GMAAlarm]	OnByDefault=	<p>X...</p> <p>Ex:OnByDefault=ACM</p>	<p>Set alarm on when activity created. Replace X with one or more of:</p> <p>A=Appointment</p> <p>C=CallBack</p> <p>D=To-do</p> <p>E=Event</p> <p>M=Message</p> <p>O=Other</p> <p>Q=Queued e-mail</p> <p>S=Salespotential</p> <p>T=Next action</p>
User	[GMAAlarm]	PlaySound=	Path to.WAV file.	Plays the specified .WAV sound file when any alarm appears.
User	[GMAAlarm]	RunOnGMClose=	0/1	1 ->GoldAlarm starts when GoldMine is closed.
User	[GMAAlarm]	ShowUpcoming=	0/1	(Don't)Show upcoming alarms in GMALARM.EXE.
User	[GoldMine]	AlarmFreq=	#	Specifies the number of seconds GoldMine scans for alarms.

User	[GoldMine]	AllowSQLPgDn=	0/1	Disallow/allowup/down paging For small SQL databases (fewer than 10,000 records) other than MS-SQL and Sybase. This functionality is provided by default for MS-SQL and Sybase. See 1222 notes.
User	[GoldMine]	BoldFont=	0/1(default=0)	Instructs GoldMine 95 to use a normal/bold font.
User	[GoldMine]	CompTimer=	0/1	(Don't)Start timer when completing activities.
User	[GoldMine]	DupCheckExt=	0/1 (default=1)	Exclude/Include extension1 in match when checking phone1 for duplicates.
User	[GoldMine]	Epoch	mm/dd/yy	Specifies the cutoff date to default to the 21st century. Specifying 01/01/50 would make it so that any year entered before 50 would default to 20xx, after 50 would default to 19xx.
User	[GoldMine]	Followup=	0/1(default=0)	(Don't)Automatically check the schedule a follow up.
User	[GoldMine]	MacFile=	UserName	Allows other users to share macros of UserName specified.
User	[GoldMine]	MinFindObj=	0/1(default=0)	Expand/Shrink the Contact Listing window by default.
User	[GoldMine]	MSMailHistory=	0/1	(Don't)Create a history record after sending an Internet e-mail message via Microsoft Outlook.
User	[GoldMine]	MSSQLMaxBrowseRecs=	###(default is 2000)	Option to increase the maximum records displayed in a browse window for MS-SQL 6.5/7.xand Sybase. See 1222 notes.
User	[GoldMine]	NewMenu=	0/1	Disable/enable new menus
User	[GoldMine]	PhoneMsgEmail=	0/1	Stores phone messages as scheduled call (0), default for version 4.0, or e-mail message (1), as was done in version 3.2.
User	[GoldMine]	PubFilter=	#	Show the username/public filters list when the filter window is opened.
User	[GoldMine]	PubForm=	0/1 (default is 0)	Show the username/public forms list in the merge forms window.

User	[GoldMine]	ROTabs=	12 comma-separated values representing the names to display on the contact screen tabs	Default is Summary, Fields, Notes, Contacts, Profiles, Referrals, Pending, History, Links, Groups, Tracks, Opptys, Projects
User	[GoldMine]	ROTitle=	1/2	GoldMine to display the Company/Contact name in the title bar
User	[GoldMine]	SaveRemoteLic=	Path to save file with trailing \	Creates License.dbf file as undocked users are setup. See SP Tech Supp.
User	[GoldMine]	SplusLink=	ACDT	Activate the Schedule Plus link.
User	[GoldMine]	SQLQueryLimit=	##	Specify the maximum number of records loaded in the SQL Query list view. The default remains 10,000 records. The limitation is not a locking issue, but a memory limitation of loading so much data into the list view.
User	[GoldMine]	SyncActiveObj=	0/1	(Don't)Sync Contact record display with highlighted item in Activity List display.
User	[GoldMine]	SyncGroupObj=		(Don't)Sync Contact record display with highlighted item in Group List display
User	[GoldMine]	UpdatePegboard=	0/1	Disable/Enable periodic updating of the Peg Board.
User	[GoldMine]	UserView=	#(default=0)	This setting specifies the default field view to show when the user logs in.
User	[GoldMine]	ZipValid=	0/1	Trun ZipCode validation off/on.
User	[GoldPager]	MaxChars=	#	Stores the maximum character width setting for the pager.
User	[GoldPager]	PIN=	#	PIN (or Personal Identification Number) of the pager being paged.
User	[GoldPager]	ShowStatus=	0/1	Allow/Disallow the pager status window to minimize.
User	[GoldPager]	Terminal=	#	Terminal number for the pager company.
User	[GraphObj]	Grid=	0/1	Turns off/on the Snap-To grid in GoldMine 95's report layout mode.
User	[HelpMenu]	Opt#=	&MenuText,Path\helpfile.hlp	Adds anoption to the Help menu to open a custom help menu for GoldMine.



User	[Info]	Dpos=	#	Startingpoint of the InfoCenter window.
User	[Info]	Lsize=	#	Size of the InfoCenter window.
User	[Info]	ShowNew=	0/1	(Don't) Show new InfoCenter items when logging in.
User	[Internet]	AllowDeleteAll=	0/1	Disallow/Allow all e-mail to be deleted from the server. 1-(default setting)?will activate the Delete All Server Mail button or menu. 0 - will deactivate the Delete All Server Mail button or menu.
User	[Internet]	AttachDir	DirectoryPath	Directs GoldMine where to put attached files. Note: trailing "\" character is required.
User	[Internet]	AutoGetMail=	0/1	(Don't) Check E-mail at every GETINTERVAL= interval.
User	[Internet]	DebugSocketPOP=	0/1	Disable/Enable debugging POP sessions. This will cause GoldMine to start logging socket conversations with POP servers to files in the temp directory. Every POP session will be logged to a separate file.
User	[Internet]	DelServerMail=	0/1	(Don't) Delete E-mail on the server upon retrieval.
User	[Internet]	ExtractEmbeddedHTML=	0/1	Suppress/Enable extraction of Embedded HTML into an attachment that can be viewed using a Web browser by pressing the launch button.
User	[Internet]	GetInterval=	#	Determine how often GoldMine checks Internet connection for waiting E-mail, in minutes.
User	[Internet]	GetOldToNew=	0/1	Sets the order of Internet messages downloaded to the E-mail Center. 0?(default) is new to old.
User	[Internet]	Interactive=	0/1	1 -> GoldMine E-mail retrieval session will be "live" and interactive. 0-> GoldMine will attempt to retrieve the E-mail on its own.
User	[Internet]	KeepOldTransfers=	0/1	Allows/Disallows transfer sets to be treated like any other e-mail attachment. The default is to always overwrite

				the existing transfer set. However, defining the setting to =1 offers users the option to overwrite or save file with another name.
User	[Internet]	LsizeC=	#	Stores the size & location of the Internet E-mail window.
User	[Internet]	LsizeR=	#	Stores the size & location of the Internet E-mail window.
User	[Internet]	MaxEmailSize=	#	LargestE-mail file GoldMine will retrieve, in Kbytes.
User	[Internet]	NewQuoteStyle=	0/1	0->Quote e-mail in reply surrounded by >. Amd ?lt;<? 1-> Quote e-mail in replay by beginning each line with ">"
User	[Internet]	OnlyGMMail=	0/1	1 ->only receive Internet E-mail created by GoldMine. 0 -> receive Internet E-mail created by anyone.
User	[Internet]	Organization=	text	Override e-mail x-organization header section with text. Default text comes from Licensed to-registration screen.
User	[Internet]	POP3_PASS=	password	Password for the POP3 connection.
User	[Internet]	POP3_Server=	servername	Server name for the POP3 connection
User	[Internet]	POP3_USER=	username	Username for the POP3 connection.
User	[Internet]	POPIdle=	##	Changes the timeout value before closing the connection to the POP3 server. This is because POP3 servers only commit changes after the connection is closed. Note that the Dial up networking connection will not be closed, only the server connection will. The default is 10 minutes.
User	[Internet]	RetrieveOverWrite=	2/4/6/7	Control show attachments are saved when a new file has the same name as an existing file. Options are: 2 - don't save the new file; 4 - assign a different name to the new file; 6 - overwrite the existing file; and 7 - bring up a dialog for the user to choose a file name (Option 7 isn't available for background mail retrieval, it

				will work just like Option 4). Name assignment is done by appending a number displayed in a set of () to the file name, so that "test.txt" will become "test(1).txt", "test(2).txt" and so on. If there are more than 64 files with the same name, a new random name will be generated.
User	[Internet]	Return_Address=	Emailaddress	User's return E-mail address.
User	[Internet]	SendQueueFor=	UserNames separated w/ semi-colon	Allows a user to send other users queued e-mail to the internet server simultaneously when auto retrieving or sending queued mail.
User	[Internet]	SendQueueWhenAutoGet=	0/1	(Don't) Send queued messages when using Auto retrieve. See 505 notes.
User	[Internet]	SigFile=	Path to text file	Appends the contents of a signature text file to a composed e-mail message.
User	[Internet]	SkipContains=	?	Specifies the value GoldMine uses to evaluate in SkipField=.
User	[Internet]	SkipExpr=	?	Specifies an expression for evaluating SkipField.
User	[Internet]	SkipField=	?	Specifies the GoldMine field to evaluate for the contents of SkipContains=.
User	[Internet]	SkipIfField=	0/1	(Don't) Check the SkipField= for the value in SkipContains= and/or SkipExpr=. If set to 0, then GoldMine will not use those values in retrieving E-mail. Note that this is only active if GoldMine is automatically retrieving E-mail (Interactive=0 and AutoGetMail=1)
User	[Internet]	SkipLarge=	0/1	(Don't) Skip retrieval of large E-mail files and attachments.
User	[Internet]	SkipNoAddress=	0/1	(Don't) Skip retrieval of E-mail that doesn't have a matching return address in a GoldMine profile.
User	[Internet]	SkipOverWriteUI=	0/1	Allow/Disallow prompt for duplicate e-mail attachment file names. Use RetrieveOverWrite= to

				determine how to name a new file with the same name as an existing file.
User	[Internet]	SocketDebug=	2	Log e-mail sessions to a file in the user's temp dir. See 1202 notes.
User	[Internet]	SMTP_Server=	servername	Name for the SMTP E-mail server.
User	[Internet]	TCPTimeOut=	##	Set the timeout for GoldMine's Internet E-Mail. This setting will tell GoldMine how many seconds to wait (Timeout) after no response from POP3 server.
User	[Internet]	UseHeaderDate=	0/1	Use date e-mail was retrieved(0)/sent(1).
User	[Internet]	UUEncodeScan=	0/1	(Don't) Decode UU-encoded MIME attachments in incoming e-mail.
User	[Internet]	WarnAboutRTF=	0/1	(Don't) Warn if the E-mail being retrieved contains Rich Text Format (RTF) codes.
User	[Modem]	AreaCode=	#	Specifies the local area code.
User	[Modem]	BaudRate=	#	Specifies the baud rate of the modem in GoldMine 2.5a.
User	[Modem]	CommPort=	#	Specifies which comm port the modem is using.
User	[Modem]	DelayTime=	#	Specifies the number of seconds to pause after dialing.
User	[Modem]	DDEDial=	&Dial,appid,[ddecmd("%s")]	Provide outbound auto dialing to a TAPI compliant device.
User	[Modem]	HangUp=	Characterstring	Specify the string to send to the modem to instruct it to hang up.
User	[Modem]	ModemInit=	Modem initstring	Specifies the modem initialization string.
User	[Modem]	ModemPrefix=	Characterstring	Instructs GoldMine to dial the numbers after the equal sign before dialing the rest of the phone number.
User	[Modem]	ModemSuffix=	Characterstring	Instructs GoldMine to dial the numbers after the equal sign after dialing the rest of the phone number.
User	[Modem]	PagerPort=	#	?
User	[Modem]	WaitForOkay=	0/1	Disable/enable having to wait for an OK from the modem, allowing GoldMine to dial (such as speed dialing on smart phones).

User	[NetUpdate]	ProxyInfo=	ftp=//your.ftp.proxy:proxy-port	AllowsNetUpdate over ftp proxy.
User	[NetUpdate]	UseProxy=	1	Allows NetUpdate over ftp proxy.
User	[OpMgr]	DefToFirstOp=	0/1	(Don't)Automatically display the first Opportunity/Project associated with a contact in the Opportunity/Project field of a Scheduled Activity window. See 822 notes.
User	[OpMgr]	Opview=	0/1	Opportunity default initial view is Opportunities/Projects.
User	[RepLayout]	Top Dock=	Toolbarname	Specifies which toolbars to display on the top of the screen.
User	[Reports]	LastRec=	#	Specifies the last report the user looked at.
User	[Reports]	RepTType=	Letter	Specifies the last report category selected.
User	[RepPreview]	Left Dock=	Toolbarname	Specifies which toolbars to display on the left side of the screen.
User	[RepPreview]	Preview=	#,...	Specifies which icons to display on the Preview icon bar.
User	[RepPreview]	RightDock=	Toolbarname	Specifies which toolbars to display on the right side of the screen.
User	[RepPreview]	Top Dock=	Toolbarname	Specifies which toolbar to display when in Report preview mode.
User	[Session]	Contact0=	Contactacct & display info	Last contact viewed. Set on exit .
User	[Sync]	CutoffDate=	Date	Specifies the synchronization cutoff date. GoldMine will update this line with the last date a successful sync was completed.
User	[Sync]	CutoffTime=	Time	Specifies the synchronization cutoff time. GoldMine will update this line with the last time a successful sync was completed.
User	[Sync]	Debug=	0/1	Remove/AddSync Stamp Conversion option to the Sync Manager's local menu. This option will convert a date and time to a SyncStamp time (first 7 characters inRecID, and SyncStamp /

				LogStamp in Log files), and vice versa. NOTE: SyncSpy is also a utility for viewing when records in GoldMine were modified. Not supported by GoldMine Software Technical Support.
User	[Sync]	DefaultLapPath=	Path	Specifies the default path to the laptop's GoldMine directory when syncing with connected notebook.
User	[Sync]	DefaultXferPath=	Path	Specifies the default path to place a transfer set in.
User	[Sync]	GMT=	#	Local timezone difference from GMT.
User	[Sync]	RetrievePath=	Path	Specifies the default path from which to retrieve a transfer set.
User	[Sync]	TempLinksPath=	Pathstring Example: TempLinksPath=C:\GM\NEWLINKS	Specify a different directory for the temp links path. When GoldMine cannot find the path specified in the linked document it will place the document in the temp links path. Default is \GOLDMINE\TMPLINKS.
User	[Sync]	UseAltDrivesOnly=	0/1	When GoldMine syncs linked documents, it will try to place the linked document in the drive specified in the original path. To instruct GoldMine to ignore the original drive and only search for the path using the drives specified in AltDrives= command, add UseAltDrivesOnly=1. To instruct GoldMine to attempt to place the document on the original before using the drives specified in AltDrives= command, add UseAltDrivesOnly=1.
User	[Tool16]	TopDock=	#	Determines which toolbars are displayed on the top menu bar.
User	[Tool16]	E-Mail=		Determines which icons show up on the E-Mail toolbar
User	[Tool16]	Left Dock=		Determines which toolbars appear docked to the left side of the screen.
User	[Tool16]	Misc=		Determines which icons show up on the Misc toolbar

User	[Tool16]	Record=		Determines which icons show up on the Record toolbar
User	[Tool16]	Schedule=		Determines which icons show up on the Schedule toolbar
User	[Tool16]	Setup=		Determines which icons show up on the Setup toolbar
User	[Tool16]	Standard=		Determines which icons show up on the Standard toolbar
User	[Tool16]	Tools=		Determines which icons show up on the Tools toolbar
User	[Toolbar]	ButtonText=	0/1	Reduces/Enlarges toolbar icon buttons and displays the name on each button.
User	[Toolbar]	FlyBy=	0/1	Turns Fly-By help off/on. Fly-By help appears in the right portion of the statusbar which is on the bottom of the GoldMine screen.
User	[Toolbar]	ToolbarSwitch=	0/1	GoldMine95's toolbars cannot/can be docked or undocked from the edges of the screen.
User	[Toolbar]	UserConfig=	0/1	Disallows/Allows user configuration of toolbars.
User	[Toolbar]	Quickhelp=	0/1	Turns off/on Quick Help for the tool bars. Quick Help Displays a brief summary of what each icon button does
User	[user_var]	FieldName=	Textstring Example: Title=Salesman	Defines user variables for a user. The &user_var macro can then be used to merge the field values using an external application, such as Word.
User	[Warning]	BrowseSort=	0/1/2	Disables/Enables pop-up of the Sorting Columns Warning window displaying Don't show this message again checkbox. Set to 2 to disable column sorting with dBASE files.